




1 打开 cd 光盘 open the CD disk




2 找到【LAXIA3-V45】软件 find the [lexia-3 v45]software.



3 安装 lexia3 软件前 请在 C 盘建立一个空的文本文件命名为【version.txt】 before you install the lexia-3 software, please install a blank file which name is [version.txt]



4 点击【instlex3】click[instlex 3]



5 安装 【enter】 install[enter]



6 选择安装的国家【语言】 choose the installation country[language]




6 选择语言【ok】choose language[ok]




7 电脑提示【please install the PROXIA recoveryCD before installing this version】the computer will remind you[please install the proxia recovery CD before installing this version]

（若有这个提示 表示有的电脑系统有缺陷 请在电脑的 c 盘建立空的文本文档命名【version】）If have such remediation, it means your computer system have disadvantage, please install a blank txt file named[version] in C partition.





7 选择按在 C 盘 please choose install in C Disk.



8 开始安装 start installing.




Lexia3


By ACTIA®



Operation in progress, please wait.




9 关掉 Internet 提示 close the internet tip.




10 安装完成 install finish.




11 把 lexia3 诊断设备连接—车 用短的 usb 线连接电脑【电脑提示安装 usb 驱动】 connect lexia-3 with a car, use the short usb cable connect it to computer[the computer remind you to find usb drive]




12 打开这段软件开始诊断 open the diagnose software begin diagnose




13 选择【unblock】 please choose [unblock]



13 关掉升级提示 if it ask you to update, please close it. do not update through internet.



14 选择要诊断的车【演示的车是 XM】Choose the car you are going to diagnose[the car we used to display is XM]



15 选择【xm】 choose [XM]

The Lexia office V1.4.5

CITROËN Presentation of Lexia Portal

XM

Vehicle selection

Specify the choice of vehicle and confirm.

start Lexia-3 (F:) The Lexia office V1.4.5 3:44 PM

The Lexia office V1.4.5

CITROËN Activation of Lexia 3 diagnostic tools

XM XM

Selection of the application

► **LEXIA**

SEDRE

PHYSICAL MEASUREMENT

Scantool


Select an application and confirm.

To change vehicle, close all open applications then select "selection of the vehicle" in the navigation zone or use the F9 key.


Warning: in order to renew the recorded vehicle data, you must carry out this procedure even when you change for a vehicle of the same model.

start Lexia-3 (F:) The Lexia office V1.4.5 3:45 PM

16 填写 vin 码 input vin code(you can input as our pic show)



17 选择手动激活 F3 choose manually active F3.



Information banner instructions

Activate the applications

You will activate the applications.
Please enter your RRDI code.
Then please confirm to start activation.


001

Confirmation of your RRDI code :



001

Information on your RRDI code.


firm to start




18 打开 CD 激活码计算软件【lexia3keyexe】open CD active code calculate software.




19 把 id 填入计算器中【在填写 lexia-345 的时候不要填写为 lexia-345.13】 input ID into the calculate machine[when write lexia-345 please pay attention, do not write it as lexia-345.13]








20 激活成功进入诊断 active succeed and then enter diagnose.





21 选择【test by function】choose [test by function]





22 选择 ecu 的型号【演示的是 2.0r6e bosch】choose ecu type[the one we choose to display is 2.0r6e bosch]





23 ecu 通讯 ok ecu communication ok



